SIEMENS

	Preface, Contents	
	Tutorial – Introduction	1
SIMATIC	Part 1: Creating PROFInet Components	2
Component based Automation	Part 2: Commissioning the System	3
Commissioning Systems Tutorial	Plant 1: CPU 315 with CP 343-1 PN	
	Plant 2: IE/PB Link with PROFIBUS DP Slaves	
	Plant 3: PC-Station WinLC PN with PROFIBUS-DP-Slaves	
	Literature and Links	4
	Index	

Safety Guidelines

This manual contains notices intended to ensure personal safety, as well as to protect the products and connected equipment against damage. These notices are highlighted by the symbols shown below and graded according to severity by the following texts:



Danger

indicates that death, severe personal injury or substantial property damage will result if proper precautions are not taken.



Warning

indicates that death, severe personal injury or substantial property damage can result if proper precautions are not taken.



Caution

indicates that minor personal injury can result if proper precautions are not taken.

Caution

indicates that property damage can result if proper precautions are not taken.

Notice

draws your attention to particularly important information on the product, handling the product, or to a particular part of the documentation.

Qualified Personnel

Only **qualified personnel** should be allowed to install and work on this equipment. Qualified persons are defined as persons who are authorized to commission, to ground and to tag circuits, equipment, and systems in accordance with established safety practices and standards.

Correct Usage

Note the following:



Warning

This device and its components may only be used for the applications described in the catalog or the technical description, and only in connection with devices or components from other manufacturers which have been approved or recommended by Siemens.

This product can only function correctly and safely if it is transported, stored, set up, and installed correctly, and operated and maintained as recommended.

Trademarks

SIMATIC®, SIMATIC HMI® and SIMATIC NET® are registered trademarks of SIEMENS AG.

Third parties using for their own purposes any other names in this document which refer to trademarks might infringe upon the rights of the trademark owners.

Copyright © Siemens AG 2002 All rights reserved

The reproduction, transmission or use of this document or its contents is not permitted without express written authority. Offenders will be liable for damages. All rights, including rights created by patent grant or registration of a utility model or design, are reserved.

Disclaimer of Liability

We have checked the contents of this manual for agreement with the hardware and software described. Since deviations cannot be precluded entirely, we cannot guarantee full agreement. However, the data in this manual are reviewed regularly and any necessary corrections included in subsequent editions. Suggestions for improvement are welcomed.

Siemens AG Bereich Automation and Drives Geschaeftsgebiet Industrial Automation Systems Postfach 4848, D- 90327 Nuernberg

©Siemens AG 2002 Technical data subject to change.



Preface

Purpose of the Manual

The purpose of this tutorial is to enable you to commission the specimen plant described in this document.

Required Basic Knowledge

To understand the manual, you should have general experience of automation engineering.

You should also be familiar with working on computers or PC-type machines (for example, programming devices) with the Windows 2000 operating system. Since SIMATIC iMap uses the STEP 7 platform, you should also be familiar with working with the standard software described in the "Programming with STEP 7 V5.2" manual.

Where is this Manual valid?

The manual is valid for the SIMATIC iMap V1.2 software package.

Place of this Documentation in the Information Environment

This manual is part of the SIMATIC iMap documentation package. The documentation is installed with the software and includes the following electronic manuals in PDF format:

- Component Based Automation and SIMATIC iMap
- Getting Started with SIMATIC iMap
- Commissioning Systems, Tutorial

The entire documentation is available for you as HTML help.

Content of this tutorial

The tutorial contains

- A description of the overall plant
- Part 1- Instructions for creating the PROFInet components and
- · Part 2Instructions for commissioning the system.

Conventions

Menu commands are printed in bold print, for example, **Project > Save**.

Further Support

If you have any technical questions, please get in touch with your Siemens representative or agent responsible.

http://www.siemens.com/automation/partner

http://www.ad.siemens.de/cba/

Training Centers

Siemens offers a number of training courses to familiarize you with the SIMATIC S7 automation system. Please contact your regional training center or our central training center in D 90327 Nuremberg, Germany for details:

Telephone: +49 (911) 895-3200.
Internet: http://www.sitrain.com

A&D Technical Support

Worldwide, available 24 hours a day:



Worldwid	le (Nuernberg)				
Technica	l Support				
24 hours a	day, 365 days a year				
Phone:	+49 (0) 180 5050-222				
Fax:	+49 (0) 180 5050-223				
E-Mail:	adsupport@ siemens.com				
GMT:	+1:00				
Europe /	Africa (Nuernberg)	United St	ates (Johnson City)	Asia / Aus	stralia (Beijing)
Authoriza	ation	Technica Authoriza	l Support and ition	Technica Authoriza	Support and
Local time:	MonFri. 8:00 to 17:00	Local time:	MonFri. 8:00 to 17:00	Local time:	MonFri. 8:30 to 17:30
Phone:	+49 (0) 180 5050-222	Phone:	+1 (0) 423 262 2522	Phone:	+86 10 64 75 75 75
Fax:	+49 (0) 180 5050-223	Fax:	+1 (0) 423 262 2289	Fax:	+86 10 64 74 74 74
E-Mail:	adautorisierung@	E-Mail:	simatic.hotline@	E-Mail:	adsupport.asia@
	siemens.com		sea.siemens.com		siemens.com
GMT:	+1:00	GMT:	-5:00	GMT:	+8:00
The langua	iges of the SIMATIC Hotline	s and the au	thorization hotline are generall	y German a	nd English.

Service & Support on the Internet

In addition to our documentation, we offer our Know-how online on the internet at: http://www.siemens.com/automation/service&support

where you will find the following:

- The newsletter, which constantly provides you with up-to-date information on your products.
- The right documents via our Search function in Service & Support.
- A forum, where users and experts from all over the world exchange their experiences.
- Your local representative for Automation & Drives via our representatives database.
- Information on field service, repairs, spare parts and more under "Services".

Table of Contents

1	Tutoria	ll - Introduction	1-1
	1.1	Overview	1-1
	1.2	Description of the plants	1-2
	1.3	Examples supplied	1-3
2	Part 1:	Creating PROFInet components	2-1
	2.1	Overview - Creating PROFInet Components	
	1.2	Requirements - Creating PROFInet Components	
	1.3	Basic procedure - Creating PROFInet Components	2-3
	1.4	Plant 1: Creating PROFInet Components	
	1.5	Plant 2: Creating PROFInet Components	
	1.5.1	Creating the PROFInet Component for ET 200S with IM151/CPU	
	1.5.2	Creating the PROFInet Component for ET 200X with BM147/CPU	
	1.6	Plant 3: Creating PROFInet Components	
	1.6.1	Creating the PROFInet Component for WinLC PN	
	1.6.2	Creating the PROFInet Component for ET 200S with IM151/CPU	
	1.6.3	Creating the PROFInet Component for ET 200M	2-45
3	Part 2:	Commissioning the system	3-1
	3.1	Requirements - Commissioning the system	
	3.2	Basic procedure: Commissioning the system	
	3.3	Plant 1: CPU 315 with CP 343-1 PN	
	3.3.1	Step 1: Set up hardware	
	3.3.2	Step 2: Configure Plant 1 in SIMATIC iMap	
	1.1.3	Step 3: Assign an IP address to the CP 343-1 PN for the first time	
	1.1.4	Step 4: Check the Necessary Settings on the Engineering Station for F 14	Plant 13-
	1.1.5	Step 5: Commissioning Plant 1	3-16
	1.1.6	Step 6: Monitor Plant 1 Online	
	1.4	Plant 2: IE/PB Link with PROFIBUS DP slaves	3-22
	1.4.1	Step 1: Set up hardware	3-24
	1.4.1.1	ET 200S with IM151/CPU Hardware Set-up	3-24
	1.4.1.2	ET 200X with BM147/CPU Hardware Set-up	
	1.4.1.3	IE/PB Link Hardware Set-up	
	1.4.2	Step 2: Configure Plant 2 in SIMATIC iMap	
	1.4.3	Step 3: Assign addresses	
	1.4.3.1	Assigning an IP address to the IE/PB Link for the First Time	
	1.4.3.2 1.4.4	Assigning a PROFIBUS address to IM151/CPU for the First Time Step 4: Check the Necessary Settings on the Engineering Station for F	
	1.4.4	42	1a11(25-
	1.4.4.1	Set PG/PC Interface to TCP/IP	
	1.4.4.2	Assign PG/PC	
	1.4.5	Step 5: Commissioning Plant 2	
	1.4.6	Step 6: Monitor Plant 2 Online	
	1.5	Plant 3: PC-Station WinLC PN with PROFIBUS DP slaves	
	1.5.1	Step 1: Set up hardware	
	1.5.1.1	WinLC PN Hardware Set-up	
	1.5.1.2	ET 200M Hardware Set-up	
	1.5.1.3	ET 200S with IM151/CPU Hardware Set-up	
	1.5.2	Step 2: Configure Plant 3 in SIMATIC iMap	3-61

	1.5.3	Step 3: Assigning a PROFIBUS address to the IM151/CPU for the First 71	Time3-
	1.5.4	Step 4: Check Settings Required for Download and Online Functions	3-75
	1.5.4.1	Check Settings for Plant 3-1	3-75
	1.5.4.2	Set PG/PC Interface to TCP/IP	
	1.5.4.3	Assign PG/PC	
	1.5.4.4	Set PG/PC Interface on the WinLC PN PC Station	3-82
	1.5.5	Step 5: Commissioning Plant 3	3-86
	1.5.6	Step 6: Monitor Plant 3 Online	3-88
	1.6	Overall plant	
	1.6.1	Overall plant: Set up Hardware	
	1.6.2	Configure the Overall Plant	
	1.6.3	Check the Settings	3-96
	1.6.4	Start the Overall Plant	
	1.6.5	Monitor the Overall Plant Online	3-100
2	Literati	ure and Links	4-1

1 Tutorial - Introduction

1.1 Overview

Aim of the system commissioning tutorial

Commissioning a plant with PROFInet and PROFIBUS devices involves a number of different steps (in STEP 7, SIMATIC iMap and on the actual plant).

The aim of this tutorial is to enable you to commission the specimen plant described in this document.

Content of this tutorial

The tutorial contains

- · A description of the overall plant
- Part 1 Instructions for creating the PROFInet components and
- · Part 2 Instructions for commissioning the system.

Procedure


The examples described in this tutorial will guide you step-by-step through the process of commissioning a complex plant. You will use the projects and PROFInet components supplied to check your progress.

If you use the examples supplied as the basis for further steps, you can be sure that the commissioning will be carried out correctly.

If you prefer to use off-the-shelf PROFInet components in your SIMATIC iMap project, then you can start from **Part 2: Commissioning the system**.

1.2 Description of the plants

The overall plant is made up of three individual plants. Each plant consists of at least one PROFInet device with an Ethernet connection. If the PROFInet device is a PROFIBUS master, the plant may also contain PROFIBUS devices.



Structure of the plants

Plant	PROFInet device	PROFIBUS device	Function
Plant 1	CPU 315-2DP with a CP 343-1 PN		Processing station with conveyor belt
Plant 2	IE/PB Link	ET 200S with IM151/CPU	Conveyor station
		ET 200X with BM147/CPU basic module	
Plant 3	PC station with WinLC PN	ET 200S with IM151/CPU ET 200M with IM153	Processing station

1.3 Examples supplied

Tutorial install directory

- Depending on the installation the CBA_Tutorial install directory can be found
- on any path if you download the tutorial to your PC from the Internet or
- in the SIMATIC iMap install directory if you install it together with SIMATIC iMap version 1.2 or later.

If you download the tutorial from the Internet to your PC, you will find the following folders with the examples supplied in the tutorial install directory (**CBA_Tutorial**):

Folder	Content	
S7_Projects	STEP7 component projects	
	You can use these STEP7 projects to create PROFInet components for plants 1 to 3.	
PROFInet_Components	Ready-to-use PROFInet components for plants 1 to 3. You can import these PROFInet components into a SIMATIC iMap library.	

If you install the tutorial together with SIMATIC iMap, you will find the examples supplied in the following directories:

Folder	Content
Step7\examples\ ZEn27_04 to _08 (STEP 7 install directory)	STEP7 component projects You can use these STEP7 projects to create PROFInet components for plants 1 to 3.
\iMap\CBA_Tutorial\ Components (iMap install directory)	Ready-to-use PROFInet components for plants 1 to 3. You can import these PROFInet components into a SIMATIC iMap library.

Note

The PROFInet component for the IE/PB Link is already included with the SIMATIC iMap software.

Tip

We recommend that you first complete the individual commissioning steps and then use the sample projects and PROFInet components supplied as the basis for further steps to ensure that you complete the commissioning correctly.

2 Part 1: Creating PROFInet components

2.1 Overview - Creating PROFInet Components

You will need PROFInet components in order to configure a plant with SIMATIC iMap.

They can be created at any time – regardless of the physical hardware set-up. The PROFInet components for the plants described here are supplied with the software, however.

If you use off-the-shelf PROFInet components, you can skip this section and start directly with Part 2: System Commissioning.

Components for plants 1 to 3

Plant	PROFInet device	PROFIBUS device	PROFInet component
Plant 1	CPU 315-2DP with a CP 343-1 PN		Processing_B
Plant 2	IE/PB Link		IE-PB-Link1_5MB
		ET 200S with IM151/CPU	ET200S_Conveyor
		ET 200X with BM147/CPU basic module	ET200X_Conveyor
Plant 3	PC station with WinLC PN		Processing_A
		ET 200S with IM151/CPU	ET200S_Conveyor
		ET 200M with IM153	ET200M IO

2.2 Requirements - Creating PROFInet Components

The following software must be installed in order to create PROFInet components for plants 1 to 3:

- Windows 2000 SP3 or later
- STEP 7 V5.2 or later
- SIMATIC iMap V1.2
- The WinLC PN V1.1 software package must be installed on the local engineering station (only for plant 3).


Note

You will need administrator rights in order to install SIMATIC iMap.

You will need at least primary user rights in order to use SIMATIC iMap.

2.3 Basic procedure - Creating PROFInet Components

The PROFInet components are created using STEP 7. The following steps must be carried out for each PROFInet component:



Tip

We recommend that you first complete the individual steps for creating the PROFInet components, and then use the S7 projects and PROFInet components supplied as the basis for further steps to ensure that you complete the commissioning correctly. The relevant points in the tutorial are indicated by the following note:

Note


The finished STEP7 component project can be found in the tutorial install directory under

 $\label{lem:cba_Tutorial} $$ CBA_Tutorial\S7_Projects or under Step7\examples\ZEn27_04 to _08$

We recommend that you use the project supplied as the basis for further steps to ensure that you complete the commissioning correctly.

2.4 Plant 1: Creating PROFInet Components

For plant 1, create the PROFInet component called "Processing_B" from a CPU 315-2DP with CP 343-1PN as the controller for a machining station with conveyor belt.



The PROFInet component contains:


PROFInet component	PROFInet device	Technological function
Processing_B	242 4 DNI	Processing station with conveyor belt (S7 program with the component
		interface)

Basic procedure


The PROFInet component is created using STEP 7, essentially by applying the following steps:


- 1. In SIMATIC Manager, create a project for a component and configure the station hardware in HWConfig.
- 2. Create the interface DB for the component interface.
- 3. Create the S7 program.
- 4. Create the PROFInet component using a menu command and save it to a directory.

Configure the hardware



Create the Interface-DB





Further information...

on the interface DB and user-defined attributes can be found under "Interface DB properties" in the SIMATIC iMap Basic Help.

Creating the S7 program

Step	Procedure
1.	Create the S7 program in OB1. The following section from the OB1 is given by way of example. The sources can be found in the finished STEP7 project. //refreshing the interface db
	CALL "PN_InOut", DB41 LADDR:=W#16#110 DONE:=M30.0 ERROR:=M30.1 STATUS:=MW32
	//calling the technological function block "conveyor" CALL "CONVEYOR", DB40 ExternStop :="PN_Interface_DB".PowerOn ExternStart :="PN_Interface_DB".ExternReady RunDelay := IOPhotoEye1 :="IO_PhotoEye1" IOPhotoEye2 :="IO_PhotoEye2" IOPhotoEye3 :="IO_PhotoEye3" IOEStop :=FALSE StartNext :="PN_Interface_DB".StandBy Running :="PN_Interface_DB".Ready IOConveyorStart:="IO_ConveyorStart"
	//optical signal A "IO_ConveyorStart" = "IO_Signal" //forwarding the counter value
2	L "PN_Interface_DB".Counter_In T "PN_Interface_DB".Counter_Out
2.	Compile and test the S7 program.


Note


The finished STEP7 component project with all the necessary blocks of the S7 program can be found in the tutorial install directory under


\CBA_Tutorial\S7_Projects\300pncp or under Step7\examples\ZEn27_05.

We recommend that you use the project supplied as the basis for further steps to ensure that you complete the commissioning correctly.

Create the PROFInet components







Result: The PROFInet component is saved as an XML file and the component project is saved at the specified storage location.

Note


The finished PROFInet component can be found in the tutorial install directory under

\CBA_Tutorial\PROFInet_Components\processing_b-{...}


We recommend that you use it as the basis for further steps to ensure that you complete the commissioning correctly.


Representation in SIMATIC iMap

In SIMATIC iMap, the PROFInet component as a technological function has the following appearance:



2.5 Plant 2: Creating PROFInet Components





Each PROFInet component contains:

PROFInet component	PROFInet device	PROFIBUS device	Technological function
IE/PB Link	IE/PB Link		None
ET200S_Conveyor		ET 200S with IM151/CPU	Conveyor station (S7 program with the component interface)
ET200X_Conveyor		ET 200X with basic module BM147/CPU	Conveyor station (S7 program with the component interface)

Components supplied and reusability

- PROFInet components with various transmission speeds for the IE/PB Link are supplied with the SIMATIC iMap software.
- You can also use the PROFInet component "ET200S_Conveyor" for plant 3.
- In the example, "ET200S_Conveyor" and "ET200X_Conveyor" have the same S7 programs and the same component interfaces, i.e. the requirements and the procedure are the same for creating both PROFInet components.

2.5.1 Creating the PROFInet Component for ET 200S with IM151/CPU


For plant 2, create the PROFInet component "ET200S_Conveyor" as a controller for a conveyor belt with ET 200S.

Basic procedure


The PROFInet component is created using STEP 7, essentially by applying the following steps:

- 1. In SIMATIC Manager, create a project for a component and configure the station hardware in HW Config.
- 2. Create the interface DB for the component interface.
- 3. Create the S7 program.
- 4. Create the PROFInet component using a menu command and save it to a directory.

Configure the hardware



Create the interface DB



Further information...

on the interface DB and user-defined attributes can be found under "Interface DB properties" in the SIMATIC iMap Basic Help.

Create the S7 program

Step	Procedure
1.	Create the S7 program. The following section from the OB1 is given by way of example. The sources can be found in the finished STEP7 project.
	//refreshing the input section of the interface db
	CALL "PN_IN"
	DB_NO :="PN_IO_DB"
	RET_VAL:=MW20
	//calling the technological function block "conveyor"
	CALL "CONVEYOR" , DB40
	ExternStop :="PN_Interface_DB".ExternStart
	ExternStart :="PN_Interface_DB".ExternStop
	RunDelay :="PN_Interface_DB".RunDelay
	IOPhotoEye1 :="IO_PhotoEye1"
	IOPhotoEye2 :="IO_PhotoEye2"
	IOPhotoEye3 :="IO_PhotoEye3"
	IOEStop :=FALSE
	StartNext :=DB100.DBX8.0
	Running :=DB100.DBX8.1
	IOConveyorStart:="IO_ConveyorStart"
	//forwarding the counter value
	L "PN_Interface_DB".Counter_In
	T "PN_Interface_DB".Counter_Out
	//optical signal
	U "IO_ConveyorStart"
	= "IO_Signal"
	//refreshing the output section of the interface db
	CALL "PN_OUT"
	DB_NO :="PN_IO_DB"
	RET_VAL:=MW22
2.	Compile and test the S7 program.

Attention

Please note that the PN_IN (FC10) block at the start of the OB1 and the PN_OUT (FC11) block at the end of the OB1 both have to be called.


Note


The finished STEP7 component project with all the necessary blocks of the S7 program can be found in the tutorial install directory under


\CBA_Tutorial\S7_Projects\Et200s or under Step7\examples\ZEn27_06.

We recommend that you use the project supplied as the basis for further steps to ensure that you complete the commissioning correctly.

Create the PROFInet component







Result: The PROFInet component is saved as an XML file and the component project is saved at the specified storage location.

Note


The finished PROFInet component can be found in the tutorial install directory under

\CBA_Tutorial\S7_Projects\Et200s.

We recommend that you use it as the basis for further steps to ensure that you complete the commissioning correctly.

Representation in SIMATIC iMap

In SIMATIC iMap, the PROFInet component as a technological function has the following appearance:



2.5.2 Creating the PROFInet Component for ET 200X with BM147/CPU

For plant 2, create the PROFInet component "ET200X_Conveyor" as a controller for a conveyor belt with ET 200X.


In the example, "ET200X_Conveyor" and "ET200X_Conveyor" have the same S7 programs and the same component interfaces, i.e. the requirement and procedure for creating the PROFInet component are the same as for ET 200S with IM151/CPU.

Basic procedure


The PROFInet component is created using STEP 7, essentially by applying the following steps:

- 1. In SIMATIC Manager, create a project for a component and configure the station hardware in HWConfig.
- 2. Create the interface DB for the component interface.
- 3. Create the S7 program.
- 4. Create the PROFInet component using a menu command and save it to a directory.

Configure the hardware



Creating the Interface DB



Further information...

on the interface DB and user-defined attributes can be found under "Interface DB properties" in the SIMATIC iMap Basic Help.

Create the S7 program

Step	Procedure
1.	Create the S7 program. The following section from the OB1 is given by way of example. The sources can be found in the finished STEP7 project.
	//refreshing the input section of the interface db
	CALL "PN_IN"
	DB_NO :="PN_IO_DB"
	RET_VAL:=MW20
	//calling the technological function block "conveyor"
	CALL "CONVEYOR" , DB40
	ExternStop :="PN_Interface_DB".ExternStart
	ExternStart :="PN_Interface_DB".ExternStop
	RunDelay :="PN_Interface_DB".RunDelay
	IOPhotoEye1 :="IO_PhotoEye1"
	IOPhotoEye2 :="IO_PhotoEye2"
	IOPhotoEye3 :="IO_PhotoEye3"
	IOEStop :=FALSE
	StartNext :=DB100.DBX8.0
	Running :=DB100.DBX8.1
	IOConveyorStart:="IO_ConveyorStart"
	//forwarding the counter value
	L "PN_Interface_DB".Counter_In
	T "PN_Interface_DB".Counter_Out
	//optical signal
	U "IO_ConveyorStart"
	= "IO_Signal"
	//refreshing the output section of the interface db
	CALL "PN_OUT"
	DB_NO :="PN_IO_DB"
	RET_VAL:=MW22
2.	Compile and test the S7 program.

Attention

Please note that the PN_IN (FC10) block at the start of the OB1 and the PN_OUT (FC11) block at the end of the OB1 both have to be called.


Note


The finished STEP7 component project with all the necessary blocks of the S7 program can be found in the tutorial install directory under


\CBA_Tutorial\S7_Projects\Et200x or under Step7\examples\ZEn27_07.

We recommend that you use the project supplied as the basis for further steps to ensure that you complete the commissioning correctly.

Create the PROFInet component







Result: The PROFInet component is saved as an XML file and the component project is saved at the specified storage location.

Note

The finished PROFInet component can be found in the tutorial install directory under

\CBA_Tutorial\PROFInet_Components\et200x_conveyor-{...}

We recommend that you use it as the basis for further steps to ensure that you complete the commissioning correctly.


Representation in SIMATIC iMap


In SIMATIC iMap, the PROFInet component as a technological function has the following appearance:



2.6 Plant 3: Creating PROFInet Components

For plant 3, create PROFInet components for the PC station with WinLC PN and for the ET 200S with IM151/CPU and ET 200M devices.





Plant 3

Each PROFInet component contains:

PROFInet component	PROFInet device	PROFIBUS device	Technological function
Processing_A	PC station with WinLC PN		Processing station (S7 program with the component interface)
ET200S_Conveyor		ET 200S with IM151/CPU	Conveyor station (S7 program with the component interface)
ET200M_IO		ET 200M with IM153	Component interface only (see below)

Note

You can use the PROFInet component "ET200S_Conveyor" from plant 2 for plant 3 as well.

2.6.1 Creating the PROFInet Component for WinLC PN


For plant 3, create the PROFInet component "Processing_A" as the coordinator for several conveyor systems.

Basic procedure


The PROFInet component is created using STEP 7, essentially by applying the following steps:


- 1. In SIMATIC Manager, create a project for a component and configure the station hardware in HWConfig.
- 2. Create the interface DB for the component interface.
- 3. Create the S7 program.
- 4. Create the PROFInet component using a menu command and save it to a directory.

Configure the hardware



Create the Interface DB





Further information...

on the interface DB and user-defined attributes can be found under "Interface DB properties" in the SIMATIC iMap Basic Help.

Create the S7 program

Step	Procedure
1.	Create the program. The following section from the OB1 is given by way of example. The sources can be found in the finished STEP7 project.
	//forwards RunDelay to ORunDelay
	L "PN_Interface_DB".RunDelay
	T "PN_Interface_DB".RunDelay_Out
	//forwards EStop to OEStop
	U "PN_Interface_DB".HMIStop
	= "PN_Interface_DB".HMIStop_Out
	//increments OCnt if Cnt==OCnt
	L "PN_Interface_DB".Counter_In
	L "PN_Interface_DB".Counter_Out
	<>D
	SPB GO
	L "PN_Interface_DB".Counter_Out
	L 1
	+D
	T "PN_Interface_DB".Counter_Out
	GO: NOP 0
2.	Compile and test the S7 program.


Note


The finished STEP7 component project with all the necessary blocks of the S7 program can be found in the tutorial install directory under


\CBA_Tutorial\S7_Projects\WinLC or under Step7\examples\ZEn27_04.

We recommend that you use the project supplied as the basis for further steps to ensure that you complete the commissioning correctly.

Create the PROFInet component







Result: The PROFInet component is saved as an XML file and the component project is saved at the specified storage location.

Note


The finished PROFInet component can be found in the tutorial install directory under

\CBA_Tutorial\PROFInet_Components\processing_a-{...}

We recommend that you use it as the basis for further steps to ensure that you complete the commissioning correctly.

Representation in SIMATIC iMap

In SIMATIC iMap, the PROFInet component as a technological function has the following appearance:



2.6.2 Creating the PROFInet Component for ET 200S with IM151/CPU


For plant 2, create the PROFInet component "ET200S_Conveyor" as a controller for a conveyor belt with ET 200S.

Basic procedure


The PROFInet component is created using STEP 7, essentially by applying the following steps:

- 1. In SIMATIC Manager, create a project for a component and configure the station hardware in HW Config.
- 2. Create the interface DB for the component interface.
- 3. Create the S7 program.
- 4. Create the PROFInet component using a menu command and save it to a directory.

Configure the hardware



Create the interface DB



Further information...

on the interface DB and user-defined attributes can be found under "Interface DB properties" in the SIMATIC iMap Basic Help.

Create the S7 program

Step	Procedure
1.	Create the S7 program. The following section from the OB1 is given by way of example. The sources can be found in the finished STEP7 project.
	//refreshing the input section of the interface db
	CALL "PN_IN"
	DB_NO :="PN_IO_DB"
	RET_VAL:=MW20
	//calling the technological function block "conveyor"
	CALL "CONVEYOR", DB40
	ExternStop :="PN_Interface_DB".ExternStart
	ExternStart :="PN_Interface_DB".ExternStop
	RunDelay :="PN_Interface_DB".RunDelay
	IOPhotoEye1 :="IO_PhotoEye1"
	IOPhotoEye2 :="IO_PhotoEye2"
	IOPhotoEye3 :="IO_PhotoEye3"
	IOEStop :=FALSE
	StartNext :=DB100.DBX8.0
	Running :=DB100.DBX8.1
	IOConveyorStart:="IO_ConveyorStart"
	//forwarding the counter value
	L "PN_Interface_DB".Counter_In
	T "PN_Interface_DB".Counter_Out
	//optical signal
	U "IO_ConveyorStart"
	= "IO_Signal"
	//refreshing the output section of the interface db
	CALL "PN_OUT"
	DB_NO :="PN_IO_DB"
	RET_VAL:=MW22
2.	Compile and test the S7 program.

Attention

Please note that the PN_IN (FC10) block at the start of the OB1 and the PN_OUT (FC11) block at the end of the OB1 both have to be called.


Note


The finished STEP7 component project with all the necessary blocks of the S7 program can be found in the tutorial install directory under


\CBA_Tutorial\S7_Projects\Et200s or under Step7\examples\ZEn27_06.

We recommend that you use the project supplied as the basis for further steps to ensure that you complete the commissioning correctly.

Create the PROFInet component







Result: The PROFInet component is saved as an XML file and the component project is saved at the specified storage location.

Note


The finished PROFInet component can be found in the tutorial install directory under

\CBA_Tutorial\S7_Projects\Et200s.

We recommend that you use it as the basis for further steps to ensure that you complete the commissioning correctly.

Representation in SIMATIC iMap

In SIMATIC iMap, the PROFInet component as a technological function has the following appearance:



2.6.3 Creating the PROFInet Component for ET 200M

For plant 3, create the PROFInet component "ET200M_IO" as an I/O module.

Note


The PROFInet component ET200M_IO does not contain an S7 program. It only contains the component interface: the signal inputs are mapped directly onto the outputs of the technological function and the signal outputs onto the inputs of the technological function.

Basic procedure

The PROFInet component is created using STEP 7, essentially by applying the following steps:

- 1. In SIMATIC Manager, create a project for a component and configure the station hardware in HWConfig.
- 2. Create the interface DB for the component interface.
- 3. Create the S7 program.
- 4. Create the PROFInet component using a menu command and save it to a directory.


Configure the hardware



Note

The CPU (DP master) is not part of the PROFInet component to be created, so it is not displayed in SIMATIC iMap. It is needed in HW Config, however, for configuration purposes.

Create the Interface DB



Further information...

on the interface DB and user-defined attributes can be found under "Interface DB properties" in the SIMATIC iMap Basic Help.

Create the S7 program

The ET 200M does **not** require a separate S7 program since it is a module without its own PLC (CPU).


Note


The finished STEP7 component project with all the necessary blocks of the S7 program can be found in the tutorial install directory under


\CBA_Tutorial\S7_Projects\Et200m or under Step7\examples\ZEn27_08.

We recommend that you use the project supplied as the basis for further steps to ensure that you complete the commissioning correctly.

Create the PROFInet component







Result: The PROFInet component is saved as an XML file and the component project is saved at the specified storage location.

Note


The finished PROFInet component can be found in the tutorial install directory under

\CBA_Tutorial\PROFInet_Components\et200m_io-{...}

We recommend that you use it as the basis for further steps to ensure that you complete the commissioning correctly.

Representation in SIMATIC iMap

In SIMATIC iMap, the PROFInet component as a technological function has the following appearance:



3 Part 2: Commissioning the system

Commissioning a complex plant with PROFInet and PROFIBUS devices involves a large number of tasks. The following description guides you step-by-step through the process of commissioning three typical configurations (plants 1 to 3).

3.1 Requirements - Commissioning the system

Hardware requirements

The devices must be in working order and have the latest firmware.

Tip

In the following descriptions, the devices are assigned fixed IP and PROFIBUS addresses. If commissioning is to be successful, we recommend that you use the same addresses since they are used throughout all the examples supplied.

For the plant described here, all the IP addresses must be in the same subnet.

Software requirements

The following software must be installed on the engineering station:

- · Windows 2000 SP3 or later
- STEP 7 V5.2 or later
- SIMATIC iMap V1.2
- SIMATIC NET V6.0 SP6

Note

You will need administrator rights in order to install SIMATIC iMap.

You will need at least primary user rights in order to use SIMATIC iMap.

Requirement for configuring the plants in SIMATIC iMap

You must have created the PROFInet components and they must either be present in the file system or located in the tutorial install directory under

iMap\CBA Tutorial\components

3.2 Basic procedure: Commissioning the system

The following commissioning tasks are carried out for every device in a plant:

- On the plant:
 - Set up the hardware
 - Set addresses on the PROFIBUS devices
 - Network the device and link to engineering PC
- In STEP 7:
 - Assign IP addresses for the first time, if necessary
 - Make the download, online monitoring and diagnostics settings
- In SIMATIC iMap:
 - Configure the plant
 - Start the plant
 - Monitor the plant online and diagnose

Next steps

Start up one of the following plants:


- Plant 1: A CPU 315-2DP with CP 343-1 PN
- Plant 2: An IE/PB Link with the PROFIBUS devices ET 200S with IM151/CPU and ET 200X with BM147/CPU
- Plant 3: A PC station WinLC PN with the PROFIBUS devices ET 200S with IM151/CPU and ET 200M
- Overall plant consisting of plants 1 to 3

3.3 Plant 1: CPU 315 with CP 343-1 PN

Plant 1 consists of one PROFInet component. In the following example, this PROFInet component is the controller for a processing station with conveyor belt.

The PROFInet component contains:

- the PROFInet device, consisting of a CPU 315-2 DP, a CP 343-1 PN and the associated I/O modules
- the technological function "Processing_B", consisting of the S7 program with the component interface.



Basic procedure

The following tasks must be carried out:

- 1. Set up the plant hardware.
- 2. Configure the plant in SIMATIC iMap.
- 3. Assign an IP address to the device for the first time
- 4. Check your settings in STEP 7 in order to download the project data from SIMATIC iMap to the device and be able to monitor the plant online.
- 5. Start the plant
- 6. Monitor the plant online with SIMATIC iMap.

3.3.1 Step 1: Set up hardware

Hardware required

You will need the following S7-300 modules:

Quantity	Designation	Order no.
1 x	CPU 315-2DP	6ES7 315-2AF03-0AB0
1 x	Power supply unit PS 307 5A	6ES7 307-1EA00-0AA0
1 x	Communication processor CP 343-1 PN	6GK7 343-1HX00-0XE0
1 x	I/O modules DI8/DO8xDC24V/0.5A	6ES7 323-1BH01-0AA0

Step	Procedure
1.	Attach the modules to the rail
	Connect the CP 343-1 PN to the backplane bus via the bus connector.
2.	Connect the power supply.
3.	Wire up the I/O modules.
4.	Connect the Ethernet cable to the CP 343-1 PN.

3.3.2 Step 2: Configure Plant 1 in SIMATIC iMap

Requirements


You must have created the PROFInet components and they must either be present in the file system or located in the tutorial install directory under


iMap\CBA_Tutorial\components.

Basic procedure

- 1. Create a library in SIMATIC iMap, if it does not exist.
- 2. Import the PROFInet component from the file system to the library.
- 3. Paste the PROFInet component from the library to the SIMATIC iMap project and assign addresses
- 4. Interconnect the technological functions, if necessary, and generate the SIMATIC iMap project.


Create a Library in SIMATIC iMap







Plant 1: Import PROFInet Component

Step	Procedure
1.	In SIMATIC iMap, click in the "tutorial_lib" library window.
	If the "tutorial_lib" library is not open, open it by selecting Library > Open
2.	Import the PROFInet component from the file system to the library:
	Select Import Component from the context menu in the library window.
3.	Under "Search In", select the path Programs\Siemens\iMap\CBA_Tutorial\components.




Plant 1: Paste PROFInet Component into the Project and Assign Addresses





Interconnect Technological Functions and Generate the Project




Result: The plant is configured and can now be started.


3.3.3 Step 3: Assign an IP address to the CP 343-1 PN for the first time


Requirements

- The IP address of the CP 343-1PN must be known.
- The connection to the Ethernet LAN must be established; there must be no subnet transition (router) between the two.
- It must be possible to access the Ethernet interface of your PG/PC from STEP 7; the PG/PC interface must be set as follows: S7ONLINE [STEP 7] > TCP/IP > <network module> To set the PG/PC interface, select Options > Set PG/PC interface... in SIMATIC Manager or select Start > Simatic > SIMATIC NET > Settings > Set PG-PC interface from the Windows taskbar



 The DLC protocol (Data Link Control) must be installed on the Ethernet interface. If the DLC protocol is not installed on your PG/PC, call up the network settings (via Control Panel > Network > Protocols) and install the DLC protocol for your Ethernet connection.







3.3.4 Step 4: Check the Necessary Settings on the Engineering Station for Plant 1

Requirements

- See chapter "Requirements Commissioning the system"
- The PG/PC is linked to the CP 343-1 PN via the Ethernet.





For plants with WinLC PN

If you are using a WinLC PN, please note the following point:

If STEP 7, SIMATIC iMap and WinLC PN are on a computer - the local engineering station - then the settings for plant 3-2 apply, rather than those specified above.

3.3.5 Step 5: Commissioning Plant 1


Requirements

- · See chapter "System commissioning requirements"
- The PG/PC is linked to the CP 343-1 PN via the Ethernet.
- You have checked the settings on the engineering station.
- You have generated the project in SIMATIC iMap.
- · All the devices are switched on.

Tip: Check the generation status


To check the generation status of the device, open the properties

- · of the device in the network view
- · of the technological function in the plant view.



The generation status must be "Generated". If this is not the case, generate the project again using the **Project > Generate > Changes Only** menu command.

Procedure



Result: The device is ready for use.


3.3.6 Step 6: Monitor Plant 1 Online


With SIMATIC iMap, you can

- monitor online and diagnose the devices of the plant.
- · display and set online values.

Requirements

- See chapter "System commissioning requirements"
- The PG/ PC is linked to the PROFInet device or one of the PROFInet devices via the Ethernet.
- You have checked the settings in STEP 7.
- You have generated the project in SIMATIC iMap.
- You have downloaded the data to the device.
- The device is in RUN mode.






Display diagnostic information

In the event of an error, diagnostic information is displayed in SIMATIC iMap in both graphical and text format.


The diagnostic information for the technological functions can be found on the "Functions" tab in the diagnostic window.



Example: The interconnections have to be downloaded (**Online > Download Selected Device > Interconnection Only** menu command).

The diagnostic information for the devices can be found on the "Devices" tab in the diagnostic window.


Example: The device is not available. In this case, you will have to check the settings and the communication links.



3.4 Plant 2: IE/PB Link with PROFIBUS DP slaves

Plant 2 consists of the following devices:

- An IE/PB Link PROFInet device as the DP master with proxy functionality for the following PROFIBUS devices:
- ET 200S with IM 151/CPU as the intelligent DP slave for controlling a conveyor belt "ET200S_Conveyor"
- ET 200X with BM147/CPU as an intelligent DP slave for controlling a conveyor belt "ET200X Conveyor"



Basic procedure

The following tasks must be carried out:

- 1. Set up the plant hardware:
 - IE/PB Link
 - ET 200S with IM151/CPU
 - ET 200X with BM147/CPU
- 2. Configure the plant in SIMATIC iMap.
- 3. Assign addresses
 - Assign an IP address to the IE/PB Link for the first time.
 - Assign a PROFIBUS address to the IM151/CPU for the first time.
- 4. Check your settings in STEP 7 in order to download the project data from SIMATIC iMap to the devices of the plant and be able to monitor the plant online.
- 5. Start the plant
- 6. Monitor the plant online with SIMATIC iMap.

3.4.1 Step 1: Set up hardware

3.4.1.1 ET 200S with IM151/CPU Hardware Set-up

Hardware required

You will need the following modules:

Quantity	Designation	Order no.
1 x	Interface module IM 151 and terminating module, 1x	6ES7 151-7AA10-0AB0 / V2.0
2 x	Terminal module TM-P15S23-A1, 1x	6ES7 193-4CC30-0AA0
2 x	Terminal module TM-E15S24-A1, 5x	6ES7 193-4CA20-0AA0
2 x	Power module PM-E DC24 V, 1x	6ES7 138-4CA00-0AA0
1 x	2DI DC24V; high feature, 2x	6ES7 131-4BB00-0AB0
1 x	2DO DC24V; 0.5 A; high feature, 2x	6ES7 132-4BB00-0AB0
1 x	Bus connector	6ES7 972-0BA10-0XA0

Procedure

Step	Procedure
1.	Attach the modules to the rail
2.	Connect the power supply.
3.	Wire up the I/O modules.
4.	Connect the PG/PC to the IM151/CPU using the PG cable.
5.	Switch on the power supply to the IM151/CPU.

Note

When you **start up** the ET 200S for the first time (as-delivered state), the IM151/CPU can be accessed via MPI addresses 2, HSA 31 and 187.5 kBps. The PROFIBUS address is assigned to the IM 151/CPU via MPI after the project is generated in SIMATIC iMap.

3.4.1.2 ET 200X with BM147/CPU Hardware Set-up

Hardware required

You will need the following modules:

Quantity	Designation	Order no.
1 x	Basic module BM147/CPU	6ES7 147-1AA01-0XB0
1 x	Expansion module DI 4xDC24V	6ES7 141-1BD30 - 0XA0
1 x	Expansion module DO 4xDC24V/2A	6ES7 141-1BD40 - 0XA0

Procedure

Step	Procedure
1.	Attach the modules to the rail
2.	Set PROFIBUS address 18 on the BM 147/CPU basic module.
3.	Connect the power supply.
4.	Wire up the I/O modules.
5.	Connect the IE/PB Link to the BM 147/CPU using the PROFIBUS cable.
6.	Switch on the IE/PB Link if you have not already done so.

3.4.1.3 IE/PB Link Hardware Set-up

Hardware required

1 IE/PB Link network transition with the necessary accessories (see device manual).

Step	Procedure
1.	Attach the modules to the rail
2.	Connect the power supply.
3.	Connect the IE/PB Link to the Ethernet and PROFIBUS.
4.	Switch on the power supply.

3.4.2 Step 2: Configure Plant 2 in SIMATIC iMap

Requirements

You must have created the PROFInet components and they must either be present in the file system or located in the tutorial install directory under


iMap\CBA_Tutorial\components.

Basic procedure


- 1. Create a library in SIMATIC iMap, if it does not exist.
- 2. Import the PROFInet components from the file system to the library.
- 3. Paste the PROFInet components from the library into the SIMATIC iMap project.
- 4. Assign addresses in SIMATIC iMap .
- 5. Interconnect technological functions and generate SIMATIC iMap project.


Create a Library in SIMATIC iMap

Step	Procedure
1.	Start SIMATIC iMap:
	by double-clicking the icon or
	• by selecting Start > Programs > Component based Automation > SIMATIC iMap .
2.	Select the Library > New menu command.
3.	Under "Search in", select the path Programs\Siemens\iMap\Tutorial .
4.	Crate a new folder named "libs"





Import PROFInet Components







Paste PROFInet Components into the Project







Assign Addresses








Interconnect Technological Functions and Generate Project





Result: The plant is configured and can now be started.


3.4.3 Step 3: Assign addresses

3.4.3.1 Assigning an IP address to the IE/PB Link for the First Time


Requirements


- The IP address of the IE/PB Link must be known.
- The connection to the Ethernet LAN must be established; there must be no subnet transition (router) between the two.
 - It must be possible to access the Ethernet interface of your PG/PC from STEP 7; the PG/PC interface must be set as follows:

 S7ONLINE [STEP 7] > TCP/IP > <network module>
 To set the PG/PC interface, select **Options > Set PG/PC interface...** in SIMATIC Manager or select **Start > Simatic > SIMATIC NET > Settings > Set PG-PC interface** from the Windows taskbar



 The DLC protocol (Data Link Control) must be installed on the Ethernet interface. If the DLC protocol is not installed on your PG/PC, call up the network settings (via Control Panel > Network > Protocols) and install the DLC protocol for your Ethernet connection.







3.4.3.2 Assigning a PROFIBUS address to IM151/CPU for the First Time


In step 2, you assigned a PROFIBUS address to the IM151_CPU device in SIMATIC iMap. You will have to download this PROFIBUS address from STEP 7 via MPI to the device yourself for the first time.

Requirements

- The IM151/CPU must be STOPped.
- The PG/PC must be connected to the IM151/CPU via MPI.
- The SIMATIC iMap project must have been generated. When you open the properties of the IM151_CPU device, the generation status "Generated" must appear on the "Instance" tab. Generate the project if this is not the case.







3.4.4 Step 4: Check the Necessary Settings on the Engineering Station for Plant 2

Requirements

- See chapter "System commissioning requirements"
- The PG/PC is linked to the IE/PB Link via the Ethernet.

Check the settings

Check the following settings:

- Set PG/PC interface to TCP/IP
- Assign PG/PC

Further information


Detailed information can be found in the online help for that dialog box or in the SIMATIC iMap help topics under "Assign PG/PC".


For combination plants...

If you are using a WinLC PN, we distinguish between the two alternative set-ups:

- STEP 7 and SIMATIC iMap are on the local engineering PC, while the WinLC PN is on a remote computer. In this case, the settings for plant 3-1 apply to the entire plant.
- STEP 7, SIMATIC iMap and WinLC PN are all on one computer, namely the local engineering PC. In this case, the settings for plant 3-2 apply to the entire plant.

3.4.4.1 Set PG/PC Interface to TCP/IP





3.4.4.2 Assign PG/PC


Note


The PG/PC assignment is automatically carried out in SIMATIC iMap when the project is generated for the first time, and then whenever it is regenerated. In special cases, the PG/PC assignment cannot be carried out automatically, e.g.


- · there are several network cards on the PG/PC or
- the PG/PC interface S7ONLINE (STEP 7) is not set to TCP/IP.


In these cases, an error is signalled in the information window during generation, and you will have to assign the PG/PC as described below.


The PG/PC assignment is not required if a local WinLC incorporating a network card is used.











3.4.5 Step 5: Commissioning Plant 2


Requirements

- · See Chapter "System commissioning requirements"
- The PG/PC is linked to the IE/PB Link via the Ethernet.
- The IE/PB Link is linked to the DP slaves via the PROFIBUS.
- You have checked the settings in STEP 7.
- You have generated the project in SIMATIC iMap.
- · All the devices are switched on.


Tip: Check the generation status

To check the generation status of a device, open the properties

- · of the device in the network view
- of the technological function in the plant view.



The generation status must be "Generated". If this is not the case, generate the project again using the **Project > Generate > Changes Only** menu command.



Result: The devices are ready for use.

Notes on downloading

Download the data to the DP master with proxy functionality (IE/PB Link) first, and then to the associated DP slaves.

When changes are made to the PROFIBUS within the project by removing or adding PROFIBUS devices, for example, then a download to both DP master and DP slaves is required.

The program download must be carried out first, using either:

- Download > Selected Devices > All or
- Download > Selected Devices > Program Only.

Interconnections can be downloaded later.


3.4.6 Step 6: Monitor Plant 2 Online


With SIMATIC iMap, you can

- monitor online and diagnose the devices of the plant.
- · display and set online values.

Requirements

- See Chapter "System commissioning requirements"
- The PG/ PC is linked to the IE/PB Link or one of the PROFInet devices via the Ethernet.
- You have checked the settings in STEP 7.
- You have generated the project in SIMATIC iMap.
- You have downloaded the data to the devices.
- The devices are in RUN mode.






Display diagnostic information

In the event of an error, diagnostic information is displayed in SIMATIC iMap in both graphical and text format.


The diagnostic information for the technological functions can be found on the "Functions" tab in the diagnostic window.

Example: The interconnections have to be downloaded (**Online > Download Selected Device > Interconnection Only** menu command).



The diagnostic information for the devices can be found on the "Devices" tab in the diagnostic window.

Example: The device is not available. In this case, you will have to check the settings and the communication links.



3.5 Plant 3: PC-Station WinLC PN with PROFIBUS DP slaves


Plant 3 contains a PC station WinLC PN "Processing_A" with the following PROFIBUS devices:

- ET 200S with IM151/CPU as the intelligent DP slave for controlling the conveyor belt "ET200S_Conveyor"
- ET 200M as a DP slave, I/O module "ET200M_IO" with 2 inputs and 2 outputs

The WinLC PN is a PROFInet device and a DP master with proxy functionality for the two DP slaves


Alternative set-up 3-1

STEP 7 and SIMATIC iMap are on the local engineering station, while the WinLC PN is on a remote computer.



Alternative set-up 3-2

STEP 7, SIMATIC iMap and WinLC PN are all on one computer, namely the local engineering station.



Basic procedure

The following tasks must be carried out:

- 1. Set up the plant hardware.
- 2. Set up the plant hardware:
 - IE/PB Link
 - ET 200 with IM151/CPU
 - ET 200X with BM147/CPU
- 3. Configure the plant in SIMATIC iMap.
- 4. Assign addresses
 - Assign an IP address to the IE/PB Link for the first time.
 - Assign a PROFIBUS address to the IM151/CPU for the first time.
- 5. Configure the plant in SIMATIC iMap.
- 6. Check your settings in STEP7 in order to download the project data from SIMATIC iMap to the plant and be able to monitor the plant online.
- 7. Start the plant
- 8. Monitor the plant online with SIMATIC iMap.

3.5.1 Step 1: Set up hardware

A PC station WinLC PN with the PROFIBUS devices ET 200S and ET 200M.

Set up the following hardware:

WinLC PN

We distinguish between the two following situations:

- the WinLC PN is on a remote PC
- the WinLC PN is on the local engineering station that is running SIMATIC iMap
- ET 200S with IM151/CPU
- ET 200M with BM151/CPU

3.5.1.1 WinLC PN Hardware Set-up

Hardware required

- PC with Windows 2000 SP3 or later
- PROFIBUS connection via CP 5611, for example

Procedure

Step	Procedure	
1.	Plant 3-1 only: Connect the PC to the local engineering station via the Ethernet.	
2.	Connect the PC to the DP slaves using the PROFIBUS cable.	

3.5.1.2 ET 200M Hardware Set-up

Hardware required

You will need the following modules:

Quantity	Designation	Order no.
1 x	Interface module IM 153 (from GSD file SI801DVD.200)	6ES7 153-1AA**-0XB0
1 x	Expansion module DI 4xDC24V (no power)	6ES7 321-1BH00-0AA0
1 x	Expansion module DO 4xDC24V/2A	6ES7 322-1BH00-0AA0

Step	Procedure
1.	Attach the modules to the rail
2.	Set PROFIBUS address 3 on the interface module IM 153.
3.	Connect the power supply.
4.	Wire up the I/O modules.
5.	Connect the PROFIBUS cable to the IM153-2.

3.5.1.3 ET 200S with IM151/CPU Hardware Set-up

Hardware required

You will need the following modules:

Quantity	Designation	Order no.
1 x	Interface module IM 151 and terminating module, 1x	6ES7 151-7AA10-0AB0 / V2.0
2 x	Terminal module TM-P15S23-A1, 1x	6ES7 193-4CC30-0AA0
2 x	Terminal module TM-E15S24-A1, 5x	6ES7 193-4CA20-0AA0
2 x	Power module PM-E DC24 V, 1x	6ES7 138-4CA00-0AA0
1 x	2DI DC24V; high feature, 2x	6ES7 131-4BB00-0AB0
1 x	2DO DC24V; 0.5 A; high feature, 2x	6ES7 132-4BB00-0AB0
1 x	Bus connector	6ES7 972-0BA10-0XA0

Procedure

Step	Procedure	
1.	Attach the modules to the rail	
2.	Connect the power supply.	
3.	Wire up the I/O modules.	
4.	Connect the PG/PC to the IM151/CPU using the PG cable.	
5.	Switch on the power supply to the IM151/CPU.	

Note

When you **start up** the ET 200S for the first time (as-delivered state), the IM151/CPU can be accessed via MPI addresses 2, HSA 31 and 187.5 kBps. The PROFIBUS address is assigned to the IM 151/CPU via MPI after the project is generated in SIMATIC iMap.

3.5.2 Step 2: Configure Plant 3 in SIMATIC iMap

This task can be carried out regardless of the plant's hardware set-up.

Requirements


You must have created the PROFInet components and they must either be present in the file system or located in the tutorial install directory under


iMap\CBA_Tutorial\components.

Basic procedure


- 1. Create a new library in SIMATIC iMap, if it does not exist.
- 2. Import the PROFInet components from the file system to the library.
- 3. Paste the PROFInet components from the library into the SIMATIC iMap project.
- 4. Assign addresses.
- 5. Interconnect technological functions and generate SIMATIC iMap project.


Create a Library in SIMATIC iMap







Import PROFInet Components







Paste PROFInet Components into the Project







Assign Addresses









Interconnect Technological Functions and Generate Project








Result: The plant is configured and can now be started.


3.5.3 Step 3: Assigning a PROFIBUS address to the IM151/CPU for the First Time


In step 2, you assigned a PROFIBUS address to the IM151_CPU device in SIMATIC iMap. You will have to download this PROFIBUS address from STEP 7 via MPI to the device yourself for the first time.

Requirements

- The IM151/CPU must be STOPped.
- The PG/PC must be connected to the IM151/CPU via MPI.
- The SIMATIC iMap project must have been generated. When you open the properties of the IM151_CPU device, the generation status "Generated" must appear on the "Instance" tab. Generate the project if this is not the case.







3.5.4 Step 4: Check Settings Required for Download and Online Functions

There are two different cases:

- Settings for plant 3-1: STEP 7 und SIMATIC iMap befinden sich auf dem lokalen Engineering-PC und die WinLC PN auf einem entfernten Rechner.
- Settings for plant 3-2: STEP 7, SIMATIC iMap and WinLC PN are all on the same computer the local engineering station.

3.5.4.1 Check Settings for Plant 3-1

Requirements


- · See Chapter "System commissioning requirements"
- The WinLC PN V1.1 software package must be installed on the remote PC.


Check the settings

Check the following settings:

- On the local engineering PG/PC, Set the PG/PC interface to TCP/IP
- On the local engineering PG/PC, Assign PG/PC
- On the remote PC station with WinLC PN, Set PG/PC interface to "PC internal". These settings are identical for Plant 3-1 and 3-2.

3.5.4.2 Set PG/PC Interface to TCP/IP





3.5.4.3 Assign PG/PC


Note


The PG/PC assignment is automatically carried out in SIMATIC iMap when the project is generated for the first time, and then whenever it is regenerated. In special cases, the PG/PC assignment cannot be carried out automatically, e.g.


- there are several network cards on the PG/PC or
- the PG/PC interface S7ONLINE (STEP 7) is not set to TCP/IP.


In these cases, an error is signalled in the information window during generation, and you will have to assign the PG/PC as described below.


The PG/PC assignment is not required if a local WinLC incorporating a network card is used.











3.5.4.4 Set PG/PC Interface on the WinLC PN PC Station

These settings are necessary on the WinLC PC Station of both plant 3-1 and 3-2.


Requirements


- See Chapter "System commissioning requirements"
- The WinLC PN V1.1 software package must be installed on the local engineering PC.


Note

If there is a WinLC PN on the local engineering station, the online connection between SIMATIC iMap and the devices of the plant is controlled via the station manager for the WinLC PN, so the local PC station must be configured accordingly.

Procedure







Tip

You can also set or check the access points using **Start > Settings > Control Panel > Set PG/PC Interface**.

3.5.5 Step 5: Commissioning Plant 3

Requirements

- See Chapter "System commissioning requirements"
- You have checked the settings in STEP 7.
- You have generated the project in SIMATIC iMap.
- Plant 3-1 only:


The local engineering station is linked to the remote PC (PC station with WinLC PN) via the Ethernet.

- The PC station with WinLC PN is linked to the DP slaves via the PROFIBUS.
- · WinLC PN has been started.

Tip: Check the generation status


To check the generation status of a device, open the properties

- of the device in the network view
- · of the technological function in the plant view.



The generation status must be "Generated". If this is not the case, generate the project again using the **Project > Generate > Changes Only** menu command.

Procedure



Result: The devices are ready for use.

Notes on downloading

Download the data to the DP master with proxy functionality (WinLC PN) first, and then to the associated DP slaves.

When changes are made to the PROFIBUS within the project by removing or adding PROFIBUS devices, for example, then a download to both DP master and DP slaves is required.

The program download must be carried out first, using either:

- Download > Selected Devices > All or
- Download > Selected Devices > Program Only.


Interconnections can be downloaded later.


3.5.6 Step 6: Monitor Plant 3 Online

Requirements

- See Chapter "System commissioning requirements"
- The PG/ PC is linked to the PC station or one of the PROFInet devices via the Ethernet.
- You have checked the settings in STEP 7.
- You have generated the project in SIMATIC iMap.
- You have downloaded the data to the devices.
- The WinLC PN is in RUN or RUN-P mode, and the IM151/CPU is in RUN mode.

Procedure






Display diagnostic information


In the event of an error, diagnostic information is displayed in SIMATIC iMap in both graphical and text format.

The diagnostic information for the technological functions can be found on the "Functions" tab in the diagnostic window.

Example: The interconnections have to be downloaded for the ET200M (**Online > Download Selected Device > Interconnection Only** menu command).



The diagnostic information for the devices can be found on the "Devices" tab in the diagnostic window.



Example: The device is not available. In this case, you will have to check the settings and the communication links.

3.6 Overall plant


3.6.1 Overall plant: Set up Hardware


You can combine plants 1 to 3 to form an overall plant. The procedure is as follows:


Step	Procedure
1.	Set up all the devices as described for plants 1 to 3.
2.	Connect the CP 343-1 PN, the IE/PB Link and the PC station with the WinLC PN via the Ethernet.
3.	Connect the engineering PC (running SIMATIC iMap) with the above devices via the Ethernet.

3.6.2 Configure the Overall Plant

Configure the overall plant in SIMATIC iMap







Result: The overall plant is now configured in SIMATIC iMap.

3.6.3 Check the Settings

Requirement

For the overall plant, STEP 7 and SIMATIC iMap are on the local engineering station, while the WinLC PN is on a remote computer.


Check the settings


Check the following settings:

- On the local engineering PG/PC, Set the PG/PC interface to TCP/IP
- On the local engineering PG/PC, Assign PG/PC
- On the remote PC station with WinLC PN, Set PG/PC interface to "PC internal".

3.6.4 Start the Overall Plant

Start the overall plant





Result: The devices are ready for use.

Notes on downloading

Download the data to the DP master(s) with proxy functionality (WinLC PN, IE/PB Link) first, and then to the associated DP slaves.

When changes are made to the PROFIBUS within the project by removing or adding PROFIBUS devices, for example, then a download to both DP master and DP slaves is required.


The program download must be carried out first, using either:

- Download > Selected Devices > All or
- Download > Selected Devices > Program Only.

Interconnections can be downloaded later.

3.6.5 Monitor the Overall Plant Online

Monitor the overall plant online



4 Literature and Links

Requirement

- · the SIMATIC Manual Collection, which contains all the current manuals, or
- an Internet connection. Here you will find constantly updated information in the form of FAQs and manuals and software for downloading.

Literature and links

Links to manuals containing further information about the devices and on working with SIMATIC iMap are given below.

Title	Link or download address
SIMATIC iMap manuals	SIMATIC iMap Manuals
S7-CPs Manual / Part B2 Description of the CP 343-1 PN	Description of CP 343-1 PN
Edition 04	
SIMATIC NET IE/PB Link Gateway	Description of IE/PB Link
Edition 11/2002	
SIMATIC Component based Automation - WinLC PN Addendum to WinAC Basis V3.0 Edition: 07/2001	Description of WinLC PN
SIMATIC Distributed I/O System ET 200S Edition 12/2001	Distributed I/O System ET 200S
SIMATIC ET 200S Interface Module IM 151-7 CPU	SIMATIC ET 200S Interface Module IM151/CPU
Edition 09/2002	
SIMATIC Distributed I/O System ET 200X	Distributed I/O System ET 200X
Edition 05/2001	
SIMATIC ET 200X Basic module BM147/CPU	SIMATIC ET 200X Basic Module BM147/CPU
Edition 07/1999	
SIMATIC Distributed I/O System ET 200M	Distributed I/O System ET 200M
Edition 07/00	
SIMATIC Manual Collection	SIMATIC Manual Collection
Edition 11/2002	
Information on Component based Automation	Component based Automation

Index

A	Requirements2-2
A	WinLC PN2-31
Addressing tips3-1	D
assign IP addresses	Ь
WinLC PN3-68	DB1002-7, 2-8, 2-14, 2-30
Assign IP addresses	Description of the plant 1-2
CP 343-1 PN3-11	Documentation4-1
IE/PB-Link3-32	E
WinLC PN3-68	E
Assign PG/PC3-43, 3-45, 3-78	ET 200M Hardware set-up3-60
Assigning a PROFIBUS address to ET200S for	Examples 1-3
the first time3-39, 3-72	Examples supplied1-1, 1-3
Attribute2-14, 2-30	F
Attributes2-7, 2-8	F
В	FAQs4-1
Dania manadawa	G
Basic procedure	_
Comissioning the system3-2	Generate project
Basic procedure - Creating PROFInet	generation status 3-16
components2-3	Н
C	
ODA 4.4	Hardware set-up
CBA4-1	ET 200S 3-24, 3-61
Check settings	ET 200X
Overall plant	Overall plant
Plant 13-43	1
Plant 2	•
Plant 33-76	IE/PBlink - Hardware set-up3-25
Commissioning the system	Import PROFInet components
Plant 13-16	Plant 1 3-6
Plant 2	Plant 23-28
Plant 3	Plant 3 3-65
Component based Automation4-1	Information 4-1
Component project2-10, 2-12	Install directory 1-1, 1-3
Configure plant in SIMATIC iMap3-4	Interconnect technological functions and
Overall plant3-94, 3-96	generate project3-10, 3-34, 3-70
Plant 2	Plant 23-34
Plant 3	Plant 3 3-70
Configure plant in SIMATIC iMap- Basic procedure	Interface DB2-4, 2-7, 2-8
·	Interface-DB2-14, 2-30
plant 1	Internet 4-1
Create library3-5, 3-26, 3-63	L
Creating PROFInet components2-1	L
ET200S2-15, 2-39	Links 4-1
ET200X2-22	Literature and Links 4-1
CRU 315 3DD with CR 343 1DN	Internet 4-1
CPU 315-2DP with CP 343-1PN2-4	
ET 200M2-46	

M

Manual Collection4-1
Monitor online
Overall plant 3-101
plant 1 3-18
Plant 2
Plant 3 3-89
0
Overview
Creating PROFInet components2-1
Overall plant1-2
System Commissioning 3-1
Tutorial1-1
Р
Paste PROFInet components into the project
and assign addresses
IE-PB-Link 1_5MB 3-30
Processing_A3-67
Processing_B3-8
R
Requirements2-2, 3-1
Software 3-1
S
Set PG/PC interface to TCP/IP 3-44, 3-77
SIMATIC Manual Collection4-1
Software requirements3-1
Start the overall plant
Overall plant
Т
Tips1-1, 3-1, 3-16
On generation status
on using the tutorial1-1
•
W
•